


Vario L3 Windows 7 Support

The Windows 7 Operating System includes most drivers required by the Vario 13 Digital Signage product. The exception is an IrDA Standard Driver which was included in both Windows XP and Windows Vista operating Systems but has been left out of the Windows 7 Operating System.

By Default, the IrDA should be Disabled in the System BIOS so when you install Windows 7, you should have all hardware devices recognised automatically, including Graphics Adapter, Audio and LAN.

If IrDA is Enabled, then the following error message will be shown in Device Manager





To overcome this, either Disable the IrDA within the System BIOS, or alternatively update the driver from the Microsoft Web Site using Windows Update.

Windows Update can be accessed via
Control Panel >System And Security > Windows Update > Select Options to Install

Control Panel > System and Security > Windows Update > Select updates to install

Select the updates you want to install

	Name	Size	
Important (11)	Windows 7 (10)		
	<input checked="" type="checkbox"/> (Standard Infrared Port) driver update for Built-in Infrared Device	26 KB	Windows Malicious Software Removal Tool - October 2009 (KB890830) After the download, this tool runs one time to check your computer for infection by specific, prevalent malicious software (including Blaster, Sasser, and Mydoom) and helps remove any infection that is found. If an infection is found, the tool will display a status report the next time that you start your computer. A new version of the tool will be offered every month. If you want to manually run the tool on your computer, you can download a copy from the Microsoft Download Center, or you can run an online version from microsoft.com. This tool is not a replacement for an antivirus product. To help protect your computer, you should use an antivirus product. Published: 10/13/2009  You may need to restart your computer after installing this update.  Update is ready for downloading More information Support information
Optional (36)	<input type="checkbox"/> ATI Technologies Inc. driver update for ATI Radeon HD 3200 Graphics	9.6 MB	
	<input type="checkbox"/> Security Update for ActiveX Killbits for Windows 7 (KB973525)	26 KB	
	<input type="checkbox"/> Security Update for Internet Explorer 8 for Windows 7 (KB974455)	2.9 MB	
	<input type="checkbox"/> Security Update for Windows 7 (KB974571)	42 KB	
	<input type="checkbox"/> Security Update for Windows 7 (KB975467)	146 KB	
	<input type="checkbox"/> Update for Internet Explorer 8 Compatibility View List for Windows 7 (KB975364)	36 KB	
	<input type="checkbox"/> Update for Windows 7 (KB974332)	1.6 MB	
	<input type="checkbox"/> Update for Windows 7 (KB974431)	15.8 MB	
	<input checked="" type="checkbox"/> Windows Malicious Software Removal Tool - October 2009 (KB890830)	6.7 MB	
	<input type="checkbox"/> Windows Defender (1)		
	<input checked="" type="checkbox"/> Definition Update for Windows Defender - KB915597 (Definition 1.69.144.0)	12.0 MB	

Total selected: 2 important updates OK Cancel

1:52 PM 10/29/2009